

ROLLART

SETUP MANUAL

v. 2026



WORLD
SKATE

Index

- 1 Introduction..... 3**
- 2 Technical Requirements for the World Skate RollArt judging system..... 4**
 - 2.1 Technical Panel 4
 - 2.2 Judge & Referee Panel 4
 - 2.3 Network Setup 5
 - 2.3.1 How to assign static IP address using Control Panel 6
- 3 Software Installation and PC Setup 8**
 - 3.1 Technical Panel installation 8
 - 3.1.1 Check the database configuration..... 10
 - 3.2 Judge & Referee Panel installation 11
 - 3.3 PC Setup..... 13
 - 3.3.1 Power Management..... 13
 - 3.3.2 Lid Operation..... 14
 - 3.3.3 Firewall and general settings..... 14
- 4 Pre-competition checklist 16**
 - 4.1 Using the data operator interface - quick guide..... 18
- 5 Index of tables and figures 19**

1 Introduction

This document provides an overview and basic information on installing and setting up the RollArt System.

Associated Documents

Please refer to the following documents about:

- Release Notes: [RollArt_ReleaseNotes_2026.pdf](#)
- User Manual: [RollArt_UserManual_2026.pdf](#)
- *VideoScreen manual: Rollart Video Display.pdf*

2 Technical Requirements for the World Skate RollArt judging system

IT Requirements

- ✓ 1 Laptop for **Data Operator**/Event Manager
- ✓ 3-9 Laptops or Tablets with Windows OS for the **judges/referee** (3 minimum and up to 7 currently recommended 5)
- ✓ Ethernet switch with at least 9 ports
- ✓ Network cables ranging from 3 to 15 meters for judges located further away. A total of 9 network cables is required.
- ✓ Sufficient Power plugs and extensions to connect all the systems.
- ✓ Projector to connect to the data operator PC (via HDMI).

2.1 Technical Panel

The Tech panel installs and uses the following prerequisites:

- Dot net framework version 4.7

Recommended specifications for PC or Laptop for Tech Panel.

- Intel Core i5 or better.
- 15" screen size.
- Minimum application window size: 1146 x 763.
- Screen resolution 1366x768 or better (HD+ 1600 x 900 or 1920 x 1080 recommended if available).
- Minimum 4 GB Ram, 8GB preferred.
- Windows 7 up to Windows 11.
- Ethernet Port 100M min (1G recommended to allow for video in future).
(It is not recommended to operate the system over Wi-Fi).
- HDMI 2.0 port (compatible with 1.4)

2.2 Judge & Referee Panel

The Judge & Referee panel installs and uses the following prerequisites:

- Dot net framework version 4.0

Recommended specifications for PC or Laptop for Judge & Referee Panel.

- Intel Core i5 or better.
- 10" Screen size.
- Screen resolution 1024x768 or better (1920x1080 preferred)
- Application Window Size 1018 x 720
- Minimum 2 GB Ram
- Windows 7 up to Windows 11.
- Ethernet Port 100M min (1G recommended to allow for video in future).
(It is not recommended to attempt to operate the system over WiFi).

2.3 Network Setup

Data Operator PC (tech Panel) and Judges PCs (judge panel) are all connected via star layout network, using an Ethernet switch (100M switch may be used, 1G is recommended to allow for video in the future).




Figure 1 RollArt layout

All computers must be on the same logical network, i.e., they must share the same subnet mask and IP address range.

One computer can be configured as both Judge and Referee

Network configuration sample with 5 judges, Referee and VideoScreen (external application, optional):

	IP Address	Subnet mask
Tech Panel (data operator or Assistant for SHOW groups)	192.168.0.200	255.255.255.0
Referee	192.168.0.201	255.255.255.0
Judge 1	192.168.0.202	255.255.255.0
Judge 2	192.168.0.203	255.255.255.0
Judge 3	192.168.0.204	255.255.255.0
Judge 4	192.168.0.205	255.255.255.0
Judge 5	192.168.0.206	255.255.255.0
VideoScreen (video operator)	192.168.0.209	255.255.255.0
VideoReview (cutter)	192.168.0.210	255.255.255.0

2.3.1 How to assign static IP address using Control Panel

Control Panel can be used to change the IP settings of your Windows 10 PC to static IP (other versions of Windows also allow static IP but windows will vary according to the Operating System).

1. Open Control Panel.
2. Click on Network and Internet
3. Click on Network and Sharing Center.
4. On the left panel, click the “Change adapter settings” link




Figure 2 Control Panel's Network and Sharing Center

5. Right-click the ethernet network adapter and select Properties:




Figure 3 Control Panel's network adapter properties

6. Select the Internet Protocol Version 4 (TCP/IPv4) option.
7. Click the Properties button.




Figure 4 IPv4 Properties. Setting manual IP

8. Select the "Use the following IP address" option.
9. Set the "IP address" (e.g., 192.168.7.255).
10. Set the "Subnet mask" to 255.255.255.0.
11. Leave the 'Default gateway' and 'DNS server' fields blank.
12. Click "OK" to save and close.
13. Click 'Close' to exit the network adapter properties window.

3 Software Installation and PC Setup

3.1 Technical Panel installation

The RollArt Tech Panel installer is a single installer file, which contains all prerequisites for the application.

The Tech Panel setup will install the following third-party modules:

- Crystal Reports version 13.0.35 (32 bit)
- SQLite ODBC Driver (32 bit)
- SQLite data .NET framework 4.0 (32 bit)

Installation Steps

Follow these general installation and configuration steps:

1. Run **RollArt_SetupTechPanel_5.3.exe**
2. Click on “Next” to install the tech panel into the default folder:




Figure 5 Setup TechPanel - step 1

3. Click on “Yes” if the folder already exists:




Figure 6 Setup TechPanel - Choose Yes

4. Click on “Next” to create a Desktop shortcut:




Figure 7 Setup TechPanel - step 2

5. Click on “Install” to continue with the installation:




Figure 8 Setup TechPanel - step 3

Click 'Finish' to complete the Tech Panel installation.




Figure 9 Setup TechPanel - completing setup

3.1.1 Check the database configuration

Open ODBC Data source (32 bit). You have two ways to open odbc on the tech panel pc:

- Type "odbc" in the search box on taskbar and choose "Set up ODBC data sources" from the list.
- In the Control Panel type "odbc" in the top-right box, and choose "Set up ODBC data sources (32-bit)".

Confirm the "rollerjudge" data source is present under "User DSN":




Figure 10 ODBC User DSN - check rollerjudge

Double click on “rollerjudge” and verify the Database Name:




Figure 11 ODBC User DSN - check rollerjudge path

Click on OK to close.

3.2 Judge & Referee Panel installation

The RollArt Judge & Referee Panel installer is a single installer file, which contains all prerequisites for the application.

Installation Steps

Follow these general installation and configuration steps, after network configuration:

1. Run **RollArt_SetupJudgeReferee_5.3.exe**
2. Click on “Next” to install the judge panel into the default folder:




Figure 12 Setup Judge & Referee Panel - step 1

3. Click on “Next” to create a Desktop shortcut:




Figure 13 Setup Judge Panel - step 2

4. Click on “Install” to continue with the installation:




Figure 14 Setup Judge Panel - step 4

5. At the end of the installation process click on “Finish” to open the Judge & Referee Panel and to set the Judge number and the IP address of the tech panel:




Figure 15 Change default values

The Settings window allows setting the Judge role between three different modes:

- Judge only (from 1 to 9)
- Referee only
- Judge (from 1 to 9) + Referee

Other options:

- **Enable marks for referee:** it allows to show to the referee all the Judges goes and components at the end of each segment

Save and Close to confirm the Judge Number and IP address.

3.3 PC Setup

To ensure smooth operation during competition it is recommended to ensure that all the computers are configured to eliminate interference with operation of the system due to operating system actions.

The following settings must be applied to all judge panels and to the technical panel computer.

3.3.1 Power Management

To ensure computer will not turn off during competition configure power management to “Never Turn off the display and never put the computer to sleep”.

- ✓ Control Panel\All Control Panel Items\Power Options\Edit Plan Settings




Figure 16 PC Setup - power management

3.3.2 Lid Operation

To allow Judges the option to close PC display for better view during competition set to “Do nothing on close and when the power button and the sleep button are pressed”.

- ✓ Control Panel\All Control Panel Items\Power Options\System Settings




Figure 17 PC Setup - lid operation

3.3.3 Firewall and general settings

Disable Firewall and enable Ping

If a firewall is enabled in Windows, ‘ping’ requests are blocked by default. To configure your firewall to allow pings, follow the appropriate instructions below. NOTE: You may be prompted for “administrative access” to complete these steps.

1. Search for “Windows Firewall”, and click to open it.
2. Click “Advanced Settings” on the left.
3. From the left pane of the resulting window, click “Inbound Rules”.
4. In the right panel, find the rules titled “File and Printer Sharing (Echo Request - ICMPv4-In)”.
5. Right-click each rule and choose “Enable Rule”.

Disable Virus scanner and Windows Update

In order to avoid any performance issues on your system, make sure to switch off or disable.

- ✓ Virus scanner
- ✓ Automatic Windows update

General Settings

In addition, it is recommended to switch off the WLAN card (if your notebooks feature WLAN and if you are not using WLAN). Do not use any Virtual Private Network also known as VPN.

Furthermore, it is recommended to hide the Windows Start menu (right-click the taskbar, select 'Properties', then choose 'Auto-hide the taskbar'). This is especially useful on the Judges' Panels.

Mute the system speakers to turn off sound.

4 Pre-competition checklist

Rules to ensure the correct initialization of the RollArt system for a standard competition:

- ✓ Ensure that all the computers are correctly configured and connected to the same network via lan
- ✓ Ensure that the HDMI cable is connected to the TechPanel hdmi port. Select "Settings→ Video" and click on Preview Skater:




Figure 18 Preview display score

- ✓ Run the technical panel before starting any judge's panels:



Figure 19 Tech Panel Splash screen

- ✓ Run all the judge panels. If the Tech panel button is yellow or grey the judge is not connected. When green is connected and ready to start the competition.



Figure 20 Tech panel not connected



Figure 21 Tech panel connected

- ✓ On the Technical Panel check that all the judges and the Referee are connected (green icon), after selecting the event:




Figure 23 Tech panel - judges and referee connected

Before starting a segment, check the correct skating order of the skaters and the segment parameters:




Figure 224 Check segment's parameters

4.1 Using the data operator interface - quick guide

For all disciplines:

1. Enable/Disable **CHECK**: by clicking on CHECK button. The technical panel can decide to verify all the elements manually. CHECK button is enabled by default;
2. The data operator cannot insert a new element between two consecutive elements. To do so, they must first delete existing elements by clicking the 'Delete Last' button until reaching the desired position. Then, the new element can be inserted, and any other required elements can be re-entered;
3. **AVERAGE** for the first skater: At the end of the first skater/couple/pair or group, the data operator can ask for the components to be sent by the judges, by clicking on AVERAGE button. Elements can be confirmed and updated once the average has been sent back to the judges. **AVERAGE feature moved to the Referee Panel interface**
4. **SKIP** button: use this button to skip to the next skater if the current skater is missing. It is not possible to come back to the previous skater once a skater has been confirmed as skipped
5. **PAUSE** button: use this button in case of interruption of the program (music issue or skater injury)

5 Index of tables and figures

Figure 1 RollArt layout	5
Figure 2 Control Panel's Network and Sharing Center	6
Figure 3 Control Panel's network adapter properties	6
Figure 4 IPv4 Properties. Setting manual IP	7
Figure 5 Setup TechPanel - step 1.....	8
Figure 6 Setup TechPanel - Choose Yes	8
Figure 7 Setup TechPanel - step 2	9
Figure 8 Setup TechPanel - step 3.....	9
Figure 9 Setup TechPanel - completing setup.....	10
Figure 10 ODBC User DSN - check rollerjudge	10
Figure 11 ODBC User DSN - check rollerjudge path.....	11
Figure 12 Setup Judge & Referee Panel - step 1	11
Figure 13 Setup Judge Panel - step 2.....	12
Figure 14 Setup Judge Panel - step 4.....	12
Figure 15 Change default values	13
Figure 16 PC Setup - power management.....	13
Figure 17 PC Setup - lid operation.....	14
Figure 18 Preview display score	16
Figure 19 Tech Panel Splash screen	16
Figure 21 Tech panel not connected Figure 22 Tech panel connected.....	17
Figure 24 Check segment's parameters	17